# PHL424: Radioactive decay

**Radioactive Decay:** is the process by which a nucleus of an unstable atom decreases its total energy by spontaneously emitting radiation.

- Discovered in 1897 by the French scientist Henri Becquerel.
- He place various phosphorescent salts on photographic plates and noticed that only uranium salts exposed the plates.





Henri Becquerel





# Characterization of radioactive material



Marie Curie

Henri Becquerel's discovery inspired Marie and Pierre Curie to investigate the phenomena further.

- They found that the mineral pitchblende was more active than uranium, and concluded that it must contain different radioactive substances
- From this, they discovered polonium and radium, both of them more radioactive than uranium.





Successful investigations of radioactivity

# The Nobel Prize in Physics 1903



Antoine Henri Becquerel Prize share: 1/2



Pierre Curie Prize share: 1/4



Marie Curie, née Sklodowska Prize share: 1/4





# Primary modes of radioactive decay

# Spontaneous Fission













## Primary modes of radioactive decay





# The radioactive decay law

The number of nuclei that decay is proportional to the number of radioactive nuclei N in the sample:

 $-\frac{dN}{dt} = \lambda \cdot N$ 

#### $\lambda$ is the decay constant



Decay curve for a radioactive element



Nuclear decay





# Nuclear decay with branching

The initial nucleus can decay into either of two products, e.g. in a sample of <sup>212</sup>Bi, 36% of the nuclei decay to <sup>208</sup>Tl and 64% to <sup>212</sup>Po.

Consider the case  $A \rightarrow B$  and  $A \rightarrow C$  in parallel. We have for all time t:

$$N = N_A + N_B + N_C$$



which is constant, since the total number of nuclides remain constant. Differentiating with respect to time:

$$\frac{dN_A}{dt} = -\lambda_1 \cdot N_A - \lambda_2 \cdot N_A = N_A(0) \cdot e^{-(\lambda_1 + \lambda_2) \cdot t} \qquad \lambda = \lambda_1 + \lambda_2$$

Definition of the branching ratio:

$$f_{1} = \frac{\lambda_{1}}{\lambda} \qquad f_{2} = \frac{\lambda_{2}}{\lambda}$$
  
 $\beta$ -activity:  $A_{\beta}(t) = N_{A} \cdot \lambda \cdot f_{1} = N_{A} \cdot \lambda_{1}$   
 $\alpha$ -activity:  $A_{\alpha}(t) = N_{A} \cdot \lambda \cdot f_{2} = N_{A} \cdot \lambda_{2}$ 



# Activity

✤ For lifetimes comparable or longer than the span of a human life there are no measurable changes in the activity of a sample which prohibits direct decay curve measurements. In these cases the decay rates λ are deduced from the ratio of the observed activity A to the absolute number of radioactive atoms N in a sample.

$$A = \lambda \cdot N = \lambda \cdot \frac{m}{\mu} \cdot N_A = \frac{1}{\tau} \cdot \frac{m}{\mu} \cdot N_A$$

with the molar mass  $\mu$  and the Avogadro number N<sub>A</sub>

- ✤ For example 1 MBq of tritium (<sup>3</sup>H, T<sub>1/2</sub>=12.33 [y]) corresponds to 5.59 · 10<sup>14</sup> atoms or 2.78 [ng] of mass.
- \* 1 MBq of <sup>14</sup>C ( $T_{1/2}$ =5730 [y]) corresponds to 2.6 · 10<sup>17</sup> atoms or 6 [µg] of mass.

$$A = \frac{ln2}{T_{1/2}} \cdot N \quad \to \quad N = \frac{A \cdot T_{1/2}}{ln2} = \frac{10^6 \cdot 12.33 \cdot 365 \cdot 24 \cdot 60 \cdot 60}{0.693} = 5.6 \cdot 10^{14} a toms$$



## Activity

The number of radioactive nuclei is often unknown. One can only measure the number of decays per second (decay rate). This is the reason why the activity is defined as the number of decays per second:



When at the beginning N(t=0) radioactive nuclei were present, then the activity A after the time t is given by

$$A(t) = -\frac{dN}{dt} = \lambda \cdot N_0 \cdot e^{-\lambda \cdot t} = \lambda \cdot N = \frac{N}{\tau} = A_0 \cdot e^{-\lambda \cdot t}$$





# Activity

Activity at the beginning:	A <sub>0</sub>
Activity at time t:	$A_1 = A_0 \cdot e^{-\lambda \cdot t}  \rightarrow  \frac{A_1}{A_0} = e^{-\lambda \cdot t}$
Activity at time 2t:	$A_2 = A_0 \cdot e^{-\lambda \cdot 2t} = A_1 \cdot e^{-\lambda \cdot t} = A_1 \cdot \left(\frac{A_1}{A_0}\right)$
Activity at time 3t:	$A_3 = A_0 \cdot e^{-\lambda \cdot 3t} = A_2 \cdot e^{-\lambda \cdot t} = A_2 \cdot \left(\frac{A_1}{A_0}\right) = A_1 \cdot \left(\frac{A_1}{A_0}\right)^2$
General expression:	$A_{n+1} = A_n \cdot \left(\frac{A_1}{A_0}\right) = A_1 \cdot \left(\frac{A_1}{A_0}\right)^n$

Example: The activity of a sample was measured 1000 [Bq] one hour ago. The present activity is 900 [Bq]. What is the activity in one hour?

$$A_2 = A_1 \cdot \left(\frac{A_1}{A_0}\right) = 900 \cdot \left(\frac{900}{1000}\right) = 810$$



# **Radiation protection**









$$\Omega = \frac{a^2}{4\pi \cdot R^2} = \frac{\pi \cdot r^2}{4\pi \cdot R^2}$$





# **Radiation protection**



The biological dose, sometimes also known as the dose equivalent is expressed in units of Sieverts [Sv]. This dose reflects the fact that the biological damage caused by a particle depends not only on the total energy deposited but also on the rate of energy loss per unit distance traversed by the particle.

equivalent dose	= energy dose $\cdot$ quality factor Q

radiation	quality factor Q
X-ray, γ, β	1
thermal neutrons	2.3
fast neutrons	10
$\alpha$ -particles, heavy ions	20



